

---

# CSC 580

## Cryptography and Computer Security

*Block Ciphers, DES, and AES*

---

February 6, 2018

---

---

---

---

---

---

---

---

---

### Overview

---

Today:

- HW2 solutions review
- Block ciphers, DES, and AES
  - Textbook sections 4.1, 4.2, 4.4 plus AES handout

To do before Thursday:

- Study for quiz over HW2 material
- Read textbook sections 7.1-7.6

---

---

---

---

---

---

---

---

### DES and AES for CSC 580

---

We will focus on *how to use block ciphers securely*.

Important to understand big picture issues:

- What parameters describe block ciphers?
- What properties does a good block cipher have?
- How do parameters affect those properties?
- How did parameters change historically as capabilities grew?

How block ciphers work (internals):

- We will view as a "black box" with certain I/O behavior
- Internals are interesting, but avoided here to save time

---

---

---

---


---

---

---

---

# Block Ciphers - General



## Properties of a block cipher

- Must supply a full block of input bits in order to evaluate
- Typical block sizes: 64 or 128 bits
- Every execution of the block cipher is independent of others (stream ciphers typically carry forward state)
  - However - block ciphers used in ways that carry state forward - more on modes later
- A good block cipher can be modeled as a pseudo-random permutation
  - Appears random to adversary, so no cryptanalysis - stuck doing brute force

This fits nicely with our "view symmetric ciphers as secure black boxes" approach.

---

---

---

---

---

---

---

---

---

---

# Random Block Ciphers

## The ideal (and impractical) case

A general encryption function replaces plaintexts with ciphertexts and must be reversible.

Picking a random function is like picking a random permutation of the message space.

- Permutation because 1-to-1
- Number of permutations:  $|P|!$

For a  $b$ -bit block cipher,  $|P| = 2^b$

- Number of permutations is  $(2^b)!$

For  $b=3$ , there are  $8! = 40,320$  permutations

For  $b=8$ , there are  $256! \approx 10^{507} \approx 2^{1684}$

To specify one of  $256!$  permutations you need  $\log_2(256!) \approx 1684$  bit long key

3-bit block example:

Input	Output
(0) 000	→ 011 (3)
(1) 001	→ 101 (5)
(2) 010	→ 111 (7)
(3) 011	→ 000 (0)
(4) 100	→ 110 (6)
(5) 101	→ 010 (2)
(6) 110	→ 001 (1)
(7) 111	→ 100 (4)

---

---

---

---

---

---

---

---

---

---


# Pseudorandom vs Random

How big a key do you need to specify a permutation of 64-bit values?

Answer:  $\log_2(2^{64})! \approx 10^{21}$  bits - the key alone is 1000 million TB

Consequence: Can't pick a random permutation

- Picking from a limited domain of permutations: pseudorandom permutation
- Uses a small random seed (key!) to compute random-looking data



We can formalize this into a rigorous definition - and we will later!

---

---

---

---

---

---

---

---

---

---

## Some Pre-DES Historical Notes

### Claude Shannon


- Worked for the National Defense Research Committee during WWII
- Moved to Bell Labs in 1945
- Wrote classified paper "A Mathematical Theory of Cryptography" in 1945
  - Proved security of one-time pad and the necessity of certain OTP properties for perfect security (**any cipher with perfect security** will be similar to a OTP).
  - Declassified version "Communication Theory of Secrecy Systems" - 1949
  - Defined "unicity distance" - basically how much ciphertext is needed for brute force attacker to recognize plaintext unambiguously
- Very influential paper "A Mathematical Theory of Communication" in 1948
  - Established the field of Information Theory
  - Formalized notions such as "entropy" and measuring information in bits

### Important civilian post-WWII, pre-1970 cryptography work done at IBM

- Key players: Horst Feistel, Don Coppersmith, Alan Hoffman, Alan Konheim

## Feistel Network

Based on Figure 4.3 from the textbook (corrected!)



If "F" is a pseudorandom function indexed by key  $K_1$ , transforms right-side data into a pseudo-one-time-pad for left-side.


In one round, left side is modified (substitution) then sides swapped (permutation).

- One round clearly not secure since half just carried forward
- Since one side affects the other, transformation "spreads out" (diffusion) over multiple rounds

Concepts to work through from diagram

- Requirements on F (injective? no!)
- Decryption relation to encryption

## DES - The Data Encryption Standard History



# DES - The Data Encryption Standard

## Basic Parameters, Controversy, and Context

DES parameters:

- Block size: 64 bits
- Key size: 56 bits (8 7-bit characters, with parity bits)
- Feistel network with 16 rounds
- Feistel "F function" based on 4-bit substitutions (S-boxes)

Controversy - why were changes made?

- Warning sign: DES never cleared for secret data - only "confidential"
- Changed S-boxes - do they contain a backdoor for NSA?
  - 1994: Revealed that changes protected against differential cryptanalysis - discovered in "open literature" in 1990
  - To this day: Only really practical attacks on DES are brute force
- Reduced key length - why?
  - 56-bits is "secure enough" against non-nation-state adversaries
  - But the NSA had (and still has!) a big budget for big machines

---

---

---

---

---

---

---

---


---

---

# DES - The Data Encryption Standard

## A peek inside

DES F function:



"E" is an expansion function - one input bit can affect two S-box inputs  
S-boxes are pseudo-random substitutions (with certain properties)  
P is a bit-by-bit permutation

---

---

---

---

---

---

---

---


---

---

# DES - The Data Encryption Standard

## A peek inside

What does P look like?



Moves individual bits around.

Think about doing this in software vs hardware - how efficient?

DES also includes a similar bit-by-bit "initial permutation" (and final)

**Bottom line:** DES is **not** easy/efficient to implement in software.

---

---

---

---

---

---

---

---

---

---

## DES - The Data Encryption Standard

### Efficiency and Security

From papers published 1984-1986:

- Proposed (paper) hardware estimated about 1 million encr/sec
- Actual (built) hardware ran around 300,000 encr/sec
- Best software implementation: about 2,500 encr/sec (Vax 11/780)

Question: How long on average for a brute force attack?

Part a: Using one custom HW chip

Part b: Using 1,000,000 custom HW chips

Part c: Using software

Modern technology

- General purpose hardware: approx 10,000,000 encr/sec/core
  - HW: How long to brute force on one core? On 512 cores?
- Special-purpose HW - COPACOBANA (\$10,000): 48 billion encr/sec
  - How long now?

---

---

---

---

---

---

---

---

## DES - The Data Encryption Standard

### Bottom Line

Single DES can no longer be considered secure

Triple-DES (3-DES) extends key space to  $56 \times 3 = 168$  bits

- Big enough to be secure against brute force
- Inefficient (times 3!) in software
- Still has a 64-bit block size (bad for certain applications)

Conclusions:

- Good to understand history/evolution of cryptography
- Good introduction to block cipher concepts
- But don't use DES now...

*Next: What key parameters need improvement in a replacement?*

---

---

---

---

---

---

---

---

## What Parameters are Important?

**Key size:** Can brute force a 56-bit key in a matter of days now

**Algorithm design:** DES is inefficient in software

**Block size:**

- "Collision attacks" follow "birthday problem" probabilities
  - With just 23 people, 50% chance that two have the same birthday
  - Roughly square-root of "universe size" ( $\sqrt{365} = 19.1\dots$ )
- Applies to some applications of block ciphers
  - "universe" is number of possible ciphertext outputs
  - $\sqrt{2^{64}} = 2^{32}$  - requirement for both time and space (memory)
  - Trivial by today's standards

*What values would be good today?*

---

---

---

---

---

---

---

---

## Key Size

### Is 128 bits enough?

2004 Estimate: \$100k machine breaks 56-bit DES key in 6 hours

What about a 128-bit key?

\$100k machine takes  $>10^{18}$  years [the earth is  $<10^{10}$  years old]

What if we spent \$100,000,000,000?

Would take  $>10^{12}$  years

What about Moore's law saying that in 20 years machines will be about 16,000 times faster?

Would take  $>10^8$  years

OK, what about in 40 years (machines 100 million times faster)?

Would still take  $>30,000$  years

Do you really think Moore's law will last this long?

---

---

---

---

---

---

---

---

---

---

## Block Size

### Is 128 bits enough?

Birthday attack:

- Requires  $\sqrt{2^{128}} = 2^{64}$  time and space
- Space is  $2^{64}$  128-bit entries, for a total of  $16 \cdot 2^{64} = 2^{68}$  bytes
- One terabyte is  $2^{40}$  bytes  $\rightarrow$  requires 256 million terabytes
- At \$25/TB that would cost around \$6.4 billion (plus power, ...)

Seems pretty safe...

---

---

---

---

---

---

---

---

---

---

## AES Selection Process

1993-1995: Clipper Chip fiasco

1997: Request for proposals for new standard block cipher

- Must use 128-bit block
- Must support 128-bit, 192-bit, and 256-bit keys
- Selection process through open evaluation

1999: 15 good submissions narrowed to 5 finalists

2000: Winner selected

- Winner was an algorithm named Rijndael (limited to 128-bit blocks)
- Invented/submitted by Vincent Rijmen and Joan Daemen (Belgians)

Important points:

- Very open, public process
- No secret modifications
- Not rushed



More trust!

---

---

---

---

---

---

---

---

---

---

## AES - Some Final Points

---

In 20 years, no practical cryptanalytic attacks discovered

Approved for protecting classified information

- 128 bit keys for SECRET
- 192 or 256 bit keys for TOP SECRET
- Note: implementation must be approved

Efficiency

- Works on byte/word units: Efficient in software!
- Widespread standard → special fast CPU instructions now
  - Intel AES-NI instructions: over 10 gigabits/sec on a single core!
  - OpenSSL demo...
- Still simple enough for special-purpose hardware
  - 30+ Gbps possible

---

---

---

---

---

---

---

---